

Department of Electrical Engineering  
University of Arkansas



# **ELEG 3124 SYSTEMS AND SIGNALS**

## **Ch. 2 Continuous-Time Systems**

---

**Dr. Jingxian Wu**  
**[wuj@uark.edu](mailto:wuj@uark.edu)**

# OUTLINE

---

- **Classifications of continuous-time system**
- **Linear time-invariant system (LTI)**
- **Properties of LTI system**
- **System described by differential equations**

# CLASSIFICATIONS: SYSTEM DEFINITION

- **What is system?**


- A system is a process that transforms input signals into output signals
  - Accept an input
  - Process the input
  - Send an output (also called: the **response** of the system to input)
- System examples:
  - Radio: input: electrical signals from air, output: music
  - Robot: input: electrical control signals, output: motion or action

- **Continuous-time system**

- A system in which continuous-time input signals are transformed to continuous-time output signals

- **Discrete-time system**

- A system in which discrete-time input signals are transformed to discrete-time output signals.



Continuous-time system

discrete-time system

# CLASSIFICATIONS: SYSTEM DEFINITION


---

- **Classifications**
  - Linear v.s. non-linear
  - Time-invariant v.s. time-varying
  - Dynamic v.s. static (memory v.s. memoryless)
  - Causal v.s. non-causal
  - Invertible v.s. non-invertible
  - Stable v.s. non-stable

# CLASSIFICATIONS: LINEAR AND NON-LINEAR

- **Linear system**

- Let  $y_1(t)$  be the response of a system to an input  $x_1(t)$
- Let  $y_2(t)$  be the response of a system to an input  $x_2(t)$
- The system is linear if the **superposition principle** is satisfied:
  - 1. the response to  $x_1(t) + x_2(t)$  is  $y_1(t) + y_2(t)$
  - 2. the response to  $\alpha x_1(t)$  is  $\alpha y_1(t)$



- **Non-linear system**

- If the superposition principle is not satisfied, then the system is a non-linear system

## CLASSIFICATIONS: LINEAR AND NON-LINEAR

---

- **Example: check if the following systems are linear**

- System 1:  $y(t) = \exp[x(t)]$

- System 2: charge a capacitor. Input:  $i(t)$ , output  $v(t)$

$$v(t) = \frac{1}{C} \int_{-\infty}^t i(\tau) d\tau$$

- System 3: inductor. Input:  $i(t)$ , output  $v(t)$

$$v(t) = L \frac{di(t)}{dt}$$

# CLASSIFICATIONS: LINEAR AND NON-LINEAR

---

- **Example**

- System 4: 
$$y(t) = \frac{1}{T} \int_{t-T}^t x(\tau) d\tau + B$$


- System 5: 
$$y(t) = |x(t)|$$

- System 6: 
$$y(t) = x^2(t)$$

# CLASSIFICATIONS: LINEAR V.S. NON-LINEAR

- **Example:**

- Amplitude Modulation:
  - Is it linear?




Amplitude modulation



# CLASSIFICATIONS: TIME-VARYING V.S. TIME-INVARIANT

- **Time-invariant**

- A system is time-invariant if a time shift in the input signal causes **an identical time shift** in the output signal



- **Examples**

- $y(t) = \cos(x(t))$

- $y(t) = \int_0^t x(v) dv$

# CLASSIFICATIONS: MEMORY V.S. MEMORYLESS

---

- **Memoryless system**

- If the **present value of the output** depends only on the **present value of input**, then the system is said to be memoryless (or instantaneous).
- Example: input  $x(t)$ : the current passing through a resistor  
output  $y(t)$ : the voltage across the resistor

$$y(t) = Rx(t)$$

- The output value at time  $t$  depends only on input value at time  $t$ .

- **System with memory**

- If the present value of the output depends on not only present value of input, but also previous input values, then the system has memory.
- Example: capacitor, current:  $x(t)$ , output voltage:  $y(t)$

$$y(t) = \frac{1}{C} \int_0^t x(\tau) d\tau$$

- the output value at  $t$  depends on all input values before  $t$

## CLASSIFICATIONS: MEMORY V.S. MEMORYLESS

---

- **Examples: determine if the systems has memory or not**

- $y(t) = \sum_{i=0}^N a_i x(t - T_i)$

- $y(t) = \sin(2x^2(t) + \theta)x(t)$

# CLASSIFICATIONS: CAUSAL V.S. NON-CAUSAL

---

- **Causal system**

- A system is causal if the output  $y(t_0)$  depends only on values of input for  $t \leq t_0$ 
  - The output depends on only input from the past and present
- Example

$$y(t) = \frac{1}{C} \int_0^t x(\tau) d\tau$$

- **Non-causal system**

- A system is non-causal if the output depends on the input from the future (prediction).
- Examples:

$$y(t) = x(t + a) \quad a > 0$$


$$y(t) = \frac{1}{T} \int_{-T/2}^{T/2} x(\tau) d\tau$$

- The output value at  $t$  depends on the input value at  $t + a$  (from future)
- All practical systems are causal.

# CLASSIFICATION: INVERTIBILITY

- **Invertible**

- A system is invertible if
  - by observing the output, we can determine its input.



- Question: for a system, if two different inputs result in the same output, is this system invertible?

- **Example**

$$y(t) = 2x(t)$$

$$y(t) = \cos[x(t)]$$

- If two different inputs result in the same output, the system is non-invertible

# CLASSIFICATION: STABILITY

---

- **Bounded signal**

- Definition: a signal  $x(t)$  is said to be bounded if

$$|x(t)| < B < \infty \quad \forall t$$

- **Bounded-input bounded-output (BIBO) stable system**

- Definition: a system is BIBO stable if, for any bounded input  $x(t)$ , the response  $y(t)$  is also bounded.

$$|x(t)| < B_1 < \infty \Rightarrow |y(t)| < B_2 < \infty \quad \forall t$$

- **Example: determine if the systems are BIBO stable**

$$y(t) = \exp[x(t)]$$

$$y(t) = \int_{-\infty}^t x(\tau) d\tau$$

# OUTLINE


---

- Classifications of continuous-time system
- **Linear time-invariant system (LTI)**
- Properties of LTI system
- System described by differential equations

# LTI: DEFINITION

- Linear time-invariant (LTI) system**

- Definition: a system is said to be LTI if it's linear and time-invariant



- Linear

Input:  $x(t) = a_1 x_1(t) + a_2 x_2(t) + \cdots + a_N x_N(t) = \sum_{i=1}^N a_i x_i(t)$

Output:  $y(t) = a_1 y_1(t) + a_2 y_2(t) + \cdots + a_N y_N(t) = \sum_{i=1}^N a_i y_i(t)$

- Time-invariant

Input:  $x(t) = x_i(t - t_0)$


Output:  $y(t) = y_i(t - t_0)$



# LTI: IMPULSE RESPONSE

- **Impulse response of LTI system**

- Def: the output (response) of a system when the input is a unit impulse function (delta function).
  - Usually denoted as  $h(t)$



- **For system with an arbitrary input  $x(t)$ , we want to find out the output  $y(t)$ .**
  - Method 1: differential equations
  - Methods 2: convolution integral
  - Methods 3: Laplace transform, Fourier transform,


# LTI: CONVOLUTION

- **Derivation**

- Any signal can be approximated by **the sum of a sequence of delta functions**

$$\int_{-\infty}^{+\infty} z(\tau) d\tau = \lim_{\Delta \rightarrow 0} \sum_{n=-\infty}^{+\infty} z(n\Delta) \Delta$$

$$x(t) = \int_{-\infty}^{+\infty} x(\tau) \delta(t - \tau) d\tau = \lim_{\Delta \rightarrow 0} \sum_{n=-\infty}^{+\infty} x(n\Delta) \delta(t - n\Delta) \Delta$$




# LTI: CONVOLUTION


## • Derivation

- Any signal can be approximated by the sum of a sequence of delta functions


$$x(t) = \int_{-\infty}^{+\infty} x(\tau) \delta(t - \tau) d\tau = \lim_{\Delta \rightarrow 0} \sum_{n=-\infty}^{+\infty} x(n\Delta) \delta(t - n\Delta) \Delta$$



- Time invariant




- Linear



LTI system

# LTI: CONVOLUTION

- Convolution




- Definition:** the convolution of two signals  $x(t)$  and  $h(t)$  is defined as

$$y(t) = \int_{-\infty}^{+\infty} x(\tau)h(t - \tau)d\tau$$

- The operation of convolution is usually denoted with the symbol  $\otimes$

$$y(t) = x(t) \otimes h(t) = \int_{-\infty}^{+\infty} x(\tau)h(t - \tau)d\tau$$



**For LTI system, if we know input  $x(t)$  and impulse response  $h(t)$ ,  
Then the output is  $x(t) \otimes h(t)$**

# LTI: CONVOLUTION

---

- **Examples**

$$x(t) \otimes \delta(t)$$


$$x(t) \otimes \delta(t - t_0)$$

$$x(t) \otimes u(t)$$

# LTI: CONVOLUTION

---

- Examples



# LTI: CONVOLUTION

---

- **Example**

- Obtain the impulse response of a capacitor and use it to find the unit-step response by using convolution. Assume the input is the current, and the output is the voltage. Let  $C = 1\text{F}$ .

$$v(t) = \frac{1}{C} \int_{-\infty}^t i(\tau) d\tau$$


# LTI: CONVOLUTION PROPERTIES

- Commutativity

$$x(t) \otimes y(t) = y(t) \otimes x(t)$$

– Proof:

$$x(t) \otimes y(t) = \int_{-\infty}^{+\infty} x(\tau) y(t - \tau) d\tau$$






# LTI: CONVOLUTION PROPERTIES

- **Associativity**

$$x(t) \otimes h_1(t) \otimes h_2(t) = [x(t) \otimes h_1(t)] \otimes h_2(t) = x(t) \otimes [h_1(t) \otimes h_2(t)]$$

– proof




Associativity

# LTI: CONVOLUTION PROPERTIES

- Distributivity


$$x(t) \otimes [h_1(t) + h_2(t)] = [x(t) \otimes h_1(t)] + [x(t) \otimes h_2(t)]$$

– proof



# LTI: CONVOLUTION PROPERTIES

- Examples



$$h_1(t) = \exp(-2t)u(t)$$

$$h_3(t) = \exp(-3t)u(t)$$

$$h(t) = ?$$



$$h_2(t) = 2\exp(-t)u(t)$$

$$h_4(t) = 4\delta(t)$$


# LTI: GRAPHICAL CONVOLUTION

- Graphical interpretation of convolution


$$y(t) = \int_{-\infty}^{+\infty} x(\tau)h(t-\tau)d\tau$$



– 1. Reflection  $g(\tau) = h(-\tau)$



– 2. Shift  $g(\tau - t_0) = h(-(\tau - t_0)) = h(t_0 - \tau)$



– 3. Multiplication  $x(\tau)h(t_0 - \tau)$

– 4. Integration  $y(t_0) = \int_{-\infty}^{+\infty} x(\tau)h(t_0 - \tau)d\tau$

# LTI: GRAPHICAL CONVOLUTION

---

- **Example**

$$y(t) = [2a \cdot p_{2a}(t)] \otimes [2a \cdot p_{2a}(t - a)]$$

# OUTLINE

---

- Classifications of continuous-time system
- Linear time-invariant system (LTI)
- **Properties of LTI system**
- System described by differential equations

# LTI PROPERTIES

---

- **Memoryless LTI system**

- Review: present output only depends on present input

$$y(t) = Kx(t)$$

- The impulse response of Memoryless LTI system is

$$h(t) = K\delta(t)$$

- **Causal LTI system**

- Review: output depends on only current input and past input.
- The impulse response of causal LTI system must satisfy:


$$h(t) = 0 \quad \text{for } t < 0$$

- Why?

# LTI PROPERTIES

## • Invertible LTI Systems

- Review: a system is invertible iff (if and only if) there is an inverse system that, when connected in cascade with the original system, yields an output equal to original system input



$$x(t) \otimes h(t) \otimes g(t) = x(t)$$

- For invertible LTI systems with IR (impulse response)  $h(t)$ , there exists inverse system  $g(t)$  such that

$$g(t) \otimes h(t) = \delta(t)$$

- Example: find the inverse system of LTI system  $h(t) = \delta(t - t_0)$



# LTI PROPERTIES

---

- **BIBO Stable LTI state**

- Review: a system is BIBO stable iff every bounded input produces a bounded output.
- LTI system: an LTI system is BIBO stable iff

$$\int_{-\infty}^{+\infty} |h(t)| dt < \infty$$

- Proof:

# LTI PROPERTIES

---

- **Examples**

- Determine: causal or non-causal, memory or memoryless, stable or unstable
- 1.  $h_1(t) = t \exp(-2t)u(t) + \exp(3t)u(-t) + \delta(t-1)$
- 2.  $h_2(t) = -3\exp(2t)u(t)$
- 3.  $h_3(t) = 5\delta(t+5)$

# OUTLINE

---

- Classifications of continuous-time system
- Linear time-invariant system (LTI)
- Properties of LTI system
- **System described by differential equations**

# DIFFERENTIAL EQUATIONS

---

- LTI system can be represented by differential equations

$$a_0 y(t) + a_1 y'(t) + \cdots + a_N y^{(N)}(t) = b_0 x(t) + b_1 x'(t) + \cdots + b_M x^{(M)}(t)$$

- Initial conditions:

$$\left. \frac{d^k y(t)}{dt^k} \right|_{t=0} \quad k = 0, \dots, N-1$$

- Notation: n-th derivative:

$$y^{(n)}(t) = \frac{d^n y(t)}{dt^n}$$

# DIFFERENTIAL EQUATION

---

- **Example:**

- Consider a circuit with a resistor  $R = 1$  Ohm and an inductor  $L = 1$ H, with a voltage source  $v(t) = Bu(t)$ , and  $I_o$  is the initial current in the inductor. The output of the system is the current across the inductor.
  - Represent the system with a differential equation.
  - Find the output of the system with  $I_o = 0$  and  $I_o = 1$

# DIFFERENTIAL EQUATION

$$a_0 y(t) + a_1 y'(t) + \cdots + a_N y^{(N)}(t) = b_0 x(t) + b_1 x'(t) + \cdots + b_M x^{(M)}(t)$$

$$\left. \frac{d^k y(t)}{dt^k} \right|_{t=0}$$

$$k = 0, \dots, N-1$$

- **Zero-state response**
  - The output of the system when the initial conditions are zero
  - Denoted as  $y_{zs}(t)$
- **Zero-input response**
  - The output of the system when the input is zero
  - Denoted as  $y_{zi}(t)$
- **The actual output of the system**

$$y(t) = y_{zs}(t) + y_{zi}(t)$$

# DIFFERENTIAL EQUATION

---

- **Example**
  - Find the zero-state output and zero-input response of the RL circuit in the previous example.